AGScan
USERS MANUAL

Version 0.2 / July 2007 Edition

Nicolas Mary && Rémi Cathelin



Copyright © 2006 SIGENAE / INRA
Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with the Invariant Sections being just "Background", no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License" at the end of this manual.

Revision table :

Version	*Date*	*Major modifications*	*Author(s)*
0.1	February 15th 2006	First release	R. Cathelin
0.2	July 18th 2007	Color parameters menu Customizer for default algorithm buttons Generic image opening Generic batch	N. Mary

Acknowledgment :
I wrote this guide in English having the aim to give access to AGScan to the largest possible scientific community. But English is not my mother language, so any remark about the orthography or the grammar is welcome.

INDEX

INTRODUCTION 4

Main features of AGScan 4
Vocabulary 4

GENERAL OVERVIEW 5

The process 5
File formats 6
Image quality 6
Installing AGScan on your Computer 7
Download 7
packages contents 9
Launching AGScan 9

PROCESSING STEPS 10

User interface 10
Choose color configurations 12
Loading an image file 13
Creating a grid 16
Aligning a grid on an image 18
Loading a grid 18
aligning manually a grid 19
Global alignment algorithm 21
Local alignment algorithm 23
Shortcut buttons 26
Spot detection 26
The table 27
Quantifying an alignment 28
quantifications 28
analyze your results 30
Export results 31
Processing a batch 33
Batch tab 33
Preparing the batch 34
Save/Open a batch 37

PLUGINS 38

Presentation 38
Example: the "Memory Plugin" 38

FREQUENTLY ASKED QUESTIONS 40

INDEX 41

Word Index 41
Illustration index 43

GNU GENERAL PUBLIC LICENSE 45

Introduction

This manual is aimed to provide the necessary information to biologists using AGScan image processing software. The document is split in four parts :

- Introduction
- General overview
- Processing steps
- Plugins presentation
- Frequently asked questions

A bit of history

AGScan is a micro-array image processing software developed by the SIGENAE team.
http://www.sigenae.org/
It is an evolution of BZScan : BZScan is a radioactive DNA micro-array image processing software based on the JAI library . It was developed by the TAGC (http://tagc.univ-mrs.fr/) from 2002 to 2005.

In 2005, the SIGENAE team decided that it was worthwhile to go on with the development of BZScan, and mainly by going through the new Sigenae version named AGScan.

This software is freely available using the following address:
http://mulcyber.toulouse.inra.fr/projects/agscan/

You can also download the source code, report bugs and propose enhancements at the same address.

Main features of AGScan

The main features of AGScan are :

1. Grid conception
2. Able to use single or multiple (up to 3) channel images as input
3. Image manipulation and processing based on ImageJ
4. Manual and automatic global alignment
5. Automatic local alignment
6. Automatic quantification
7. Batch processing
8. Data export
9. Plugin support, to add new file formats, alignment or quantification methods...
10. Multi-language support

These different features will be presented in the rest of this document.

Vocabulary

Image : is a file produced by a micro-array scanner and sometimes modified (cut,...).

Grid : is first a file generated by AGScan describing the way the array has been spotted. From this it can be aligned on an image and be a part of an alignment. You will see later the importance of the grid structure.

Alignment : is composed of an image and a grid. It can have several states like 'not aligned', 'globally aligned' and 'locally aligned'.

Quantification : once the alignment is finished the quantification is the process of extracting one or more figures for each spot giving an intensity value for the spot.

Batch : is a group of alignments processed by AGScan from global alignment to quantification through local alignment.

General Overview

This chapter presents an overview of the whole process, some information about image file types and quality and gives the software install procedure.

The process

To start the process you need at least :
- a micro-array image (different formats can be used),
- a grid file (generated in AGScan see next chapter section),
- AGScan installed (see install procedure below)

Notice that AGScan works with 16bits-unsigned grayscale images.
By default, AGScan input image format is the TIFF format but ISAC format (INF/IMG) is also recognized by a plugin automatically provided into all AGScan versions.

The grid file can be generated with AGScan or provided by someone having generated it. To share a grid you have to be sure that the micro-array and the definition used to scan the image are the same.

The process can be split in five steps :

- experiment image(s) loading

- grid loading

- global alignment : This step can be done by AGScan or by the user. It corresponds to the general alignment of the designed grid on the image(s).

- local alignment : This step is done by AGScan. Starting from the global alignment AGScan tries to figure out what the small local changes are to fit the sub-grids as well as possible to the image.

- quantification : This step is done by AGScan. Starting from the local alignment coordinates AGScan calculates for each spot several quantification values. These values will be presented later on.



As presented before, AGScan is able to process an image and a grid without any human help. This is a very important and user asked AGScan feature.

File formats

AGScan can load and save several file formats depending on the element. See table hereunder.

Element	*file extension*	*comments*
image [1]	**.tif** **.inf**	Standard format of compression of image without loss of information, This file is the information file of the corresponding ".img" file. Both files have to be in the same directory to be used by AGScan. This file type is named ISAC and is for example produced by the Fuji BAS5000 scanner.
grid	**.grd**[2]	This file type is produced and used by AGScan. The format is kind of XML compliant.
experiment: Alignment / quantification	**.zaf**	This file type is produced and used by AGScan. It's an archive file that contains a ".ali" file (experiment data file), a manifest file and may contains the image(s), The ".ali" format is kind of XML compliant.[3]
batch	**.bzb**[4]	This file type is produced and used by AGScan. The format is kind of XML compliant.

Notice that AGScan provides also non-openable export formats like a ".txt" output, easily usable with your favorite spreadsheet.

Image quality

Even if AGScan proposes methods for automatically align grids on image, the result depends of a lot of things like the quality of the image, the grid structure and parameters used for the alignment.

1- Be aware that the image files have to be a 16 bits format to be processed by AGScan.
2- Be careful: BZScan and AGScan .grd grid files and .bzb batch files are incompatible!
3- Never try to open a .zaf file: .ali files are not alone support
4- Be careful: BZScan and AGScan .grd grid files and .bzb batch files are incompatible!

Installing AGScan on your Computer

Download

AGScan is freely available at:
http://mulcyber.toulouse.inra.fr/projects/agscan



Just click on the “Files” subsection:



Mulcyber AGScan page

All versions of the software are available. They are named using the date of the release.

The software releases are available in two different packages: light and full versions. With the light version, Java Runtime Environment needs to be installed previously on your operating system. The full version does not need any other software, just to click on the icon!

Downloading AGScan is very easy.
First choose a release of the package. For each release, notes are available by clicking on the release name.
Next you can download the corresponding “AGScanxxxxxx.zip” file.



Download AGScan

packages contents

The “AGScanFullxxxxxx.zip” archive file contains the following directory:

The “AGScanLightxxxxxx.zip” archive file contains the following directory:

Package contents are similar except 3 elements added to the Full version:

- the install directory: contains a Java Runtime Environment
- the “AGScan.cfg” file: the launcher configuration file
- the “AGScan.exe” file : the icon to launch AGScan (on Windows OS)

Note: the Full version launcher is only usable for Windows OS.

The file structure of files is composed of:

- the “AGScanxxxxxx.jar” file is the java executable archive file
- the languages directory containing language files available in AGScan
- the “lib” directory containing AGScan libraries and dependences used by the software (ij.jar for example). Notice that the subdirectory called “plugins” of this directory contains imageJ plugins that can be used by AGScan
- the “plugins” directory containing AGScan “.class” plugins files
- the “ChangeLog.txt” file containing the history of release notes
- the “parameters.properties” file containing the current user preferences of the software

Launching AGScan

On Linux OS, use the command line:
java -Xss10m -Xmx420m -jar AGScanxxxxxx.jar

On Windows OS:
If you choose a full version: just click on the AGScan.exe icon!
You can also run the command line (or write it in a .bat file):
"java.exe" -Xss10m -Xmx420m -jar "AGScanxxxxxx.jar"

The “.jar” file name is the release name of AGScan.
Note: the “-Xss” and the “-Xmx” parameters correspond to the memory allocation given to the Java Virtual Machine(JVM) in order to support the application. If you encounter “java OutOfMemory errors” then increase the “-Xmx” value.
By default, AGScan full version is configured with 420Mo of memory allocated for the JVM.You can modify this value in the launcher configuration file (“AGScan.cfg”file).

Processing steps

This guided tour will walk us through the different parts listed hereunder :
- User interface,
- Loading an image file,
- Creating a grid,
- Aligning a grid on an image,
- The table,
- Quantifying an alignment,
- Analyzing quantification results,
- Processing a batch.

First it will start by presenting the user interface layout:

User interface



The user interface of the software wants to be simple, readable and as ergonomic as possible.
It is composed of five elements:
- The “title window”: presenting the used AGScan version, in the selected language.
- The “menu bar”: containing the different menus of the application.
- The “toolbar”: icons wich are shortcuts to some sub-menu actions.
- The “display window”: the main window containing experiment view. Several elements may be displayed in the same time (images, grids, alignments). They are open in different tabs.
- The “status bar”: displays current information like status and progress bar.

As we want the software to be simple to use we tried to place the menus in a logical order from left to right. We hope that menus are explicit enough to be easily memorized. Shortcuts to common actions have been added below the menus in order to open, align and quantify an image in three clicks! Shortcut icons are also duplicated next to each menu title to ease memorization. Notice that if you point your mouse on a shortcut, you will obtain a little description of the associated action.



Example : the “Open Image” action menu (and related toolbar item)

The first menu you can use is the “Edition>Language” one. It allows to change the language of the application menus.

Notice that you need to reload the application to apply a new language.
Note: in the current version, three languages are available: English, French and German.
There can be spelling mistakes. However it is easy to modify these faults. Indeed, all the words are stored in text files (named “messages_en.properties”, “messages_fr.properties” and “messages_de.properties”). We can even easily generate new ones in other languages. For that, it is necessary to add the new “messages_xx.properties” file into the subdirectory of AGScan named “languages”. It will be automatically recognized by the software.

Now Let us present the different steps needed to quantify an image.

Choose color configurations

A menu is available to setup the number of channels and their names for the opening of image.
Use “Edition->Color Parameters” to access this menu.



Illustration 1: 4 configurations

First, you need to choose a number of configurations (between 1 and 6). Then click on “Validate” to update the window.

Now, you see a number of text fields equal to your previous choice.

It's time to setup the configurations. Each configuration must have the following syntax :

N:Color1,Color2,Color3,...

N is the number of channels you want. For example if you want to setup a configuration for opening 4-channels images, you will enter :

4:Color1,Color2,Color3,Color4

Color1 to Color4 are the channel name.You are totally free to choose them. For example, you could choose like in the left picture :

4:Violet,Blue,Green,Yellow



Illustration 2: 2 configurations

Once, you have choose the configurations you want you can click on “Ok” to save your choices.

If you mistake unfortunately, and have less or more configurations than you want, you could change the value in the “Number of parameters” panel and click “Validate” to reupdate the window.

You must specify a number of configurations at least equal to 1.
You must fill all the fields before clicking on “OK”.
You can't setup two or more configurations with the name number of channels.

Loading an image file

Preliminary remark: an experiment can be composed of as much images as you want , but in the following chapters we will refer to a few experiments including one and two images only.

To open an image, use the “File>Open>Image” menu or the following short icon of the toolbar:



A selection window appears. Choose your type of experiment specifying the image number of channels and then clicking on “Validate” to update the window.

Notice that you can only choose a number of channels that refers to a color configuration. The default configurations available are :

1:P33
2:Cy5,Cy3

So if you want to open images with more than two channels, don't forget to use “Edition->Color parameters” (cf. 0.9 Choose color configurations).

Once you validate, you will be able to browse for each channel file of the image.

Notice that only the images files extensions that AGScan supports are visible in the file chooser, (By default “.tif” and “.inf”).

The “Properties” button allows you to give some initial parameters of the image (produced by the scanner). These parameters are stored into the general parameters of the application.

-Pixel width : width of a pixel, micrometers
-Pixel height : height of a pixel, micrometers
-Unit: image unit (QL or PSL)
-IP type: Image Plate size ,centimeters
-Latitude: dynamic range of “above number” power of 10

If you don't know where to find these parameters, ignore them (default values will be apply).

Click “OK” to load the experiment!



The image is loaded into the “Display window”.
In the case of a multi-channels experiment, the RGB image is displayed :



Once opened, you can now modify it using the different widgets disposed in the “Image” menu.



They allow to invert the LUT, to modify the contrast and the brightness, to rotate the image, to flip it horizontally or vertically. Some of these options are very interesting when you have scanned your array the wrong way. You can also select a rectangular region and crop it to create a new sub-image.
Sometimes due to low contrast or quality, the spots can be quiet difficult to locate. All these image tools can help you to visualize them. **However, you have to know that the modification of the contrast and the brightness of the image doesn't affect pixel values of the image and isn't save.**

Other general functionalities can be used in the “Display” menu.

An example: the “zoom”:

Working with images, we sometimes need a general view and sometimes a very precise one. This can be obtained by using the zoom . Clicking on the left of the progress bar will zoom out of the image, clicking in the right will zoom in the image.
When the zoom is active, the icon background becomes gray. By clicking a second time on the icon, the zoom is disable.



Example: image with zoom action enabled.



The “display” tools are :
- “tabs” or “windows”: the display mode. Each item (image, grid, alignment) is on a tab or on a distinct window, Tabs are the default display mode.
- “zoom”: disable/enable the zoom,
- “zoom window”. Allows to display a little window containing the entire image, the zoom factor applied and that show the part of the image zoomed.
- “Display the ruler”: disable/enable a ruler. Disabled by default.
- “Display the State bar”: disable/enable the status bar. Enabled by default.
-”Properties”: allows to display the properties (name,size...) of the current element displayed into the current tab or window.

By default, the display mode is “tabs”, the zoom isn't active, the ruler is disabled and the status bar is displayed. (see the image above).



On this example, the window mode is active,the status bar is hidden, the ruler is displayed and the zoom window is open (the current zoom factor is 3),

The next part will show you how to create a grid.

Creating a grid

The grid is a very important element for the image analyze. After opening an image, you have to load a grid on it and therefore you must have already define it.
Note that you can use the same grid for all your experiments that use the same spotting scheme.

So this part will show you how to create, open and modify a grid.

At first, choose the creation grid menu found in the “File>Create>New Grid” menu or in the “Grid>New Grid” menu.

A new tab and the “structure editor” will appear. The main window is divided into two parts:
– the **grid**: the graphical representation of the grid
– the **table**: a table with all the characteristics of the grid spots (number, name position). It will be describe later.


AGScan - January 27, 2005 Version
File Edition Display Image Grid Alignment Quantification Batch Tools About
GRID_1138974828336.grd
Structure editor
Number of levels : 1
Level 1 Level 2
Number of columns : 12
columns width (µm) : 375
Number of lines : 12
Height of lines (µm) : 375
spots diameter(µm) : 250
Starting position : Top Left
Spot names : CL number
Close
Name X Y R C
1 A01 187.5 187.5 1 1
2 B01 562.5 187.5 1 2
3 C01 937.5 187.5 1 3
4 D01 1312.5 187.5 1 4
5 E01 1687.5 187.5 1 5
6 F01 2062.5 187.5 1 6
7 G01 2437.5 187.5 1 7
8 H01 2812.5 187.5 1 8
9 I01 3187.5 187.5 1 9
10 J01 3562.5 187.5 1 10
11 K01 3937.5 187.5 1 11 1 1 11 250.0
Ready
1x

By default, the editor appears on a “one level” grid, So we have to introduce you the notion of **level** in the grid. A grid can have two levels representing the block and the grid.

– level1 = the block level. In fact, the spotting is usually made using a block pattern. This is usual but not always the case. The level defines a block of spots. Information needed is the dimension of a block (number and size of columns and lines) and the diameter of a spot.

– level2 = the grid level. A grid can often be compared to a set of blocks. So if you have this second level, you just need to inform how many blocks you have vertically and horizontally. So you can also notify inter-blocks space size.

To sum up, a grid is seen by AGScan as a set of elements. The smallest element is the spot. When you have two levels, a set of spots forms a block and a set of block a grid .

In the next table the first line gives you number of levels used, the second gives you the structure of the first level and the third line gives you the structure of the second level. In the last line, you can see the graphical view of the type of spotting pattern you have used.

1 level	*2 levels*	*2 levels*
20 x 12 spots	**12 x 12 spots**	**1 x 1 spots**
-	**4 x 2 blocks**	**10 x 10 blocks**
		

Examples of grids

The grid, the table and the editor are linked. So, be aware that you need to move on an other box or hit <ENTER> (carriage return) after having entered a value in each text box of the “grid structure editor” in order to synchronize the view of the grid .

You have now define your grid and you can save it. The default proposed name of the saved file has no sense. It is just created randomly in order to be unique.
The resulting file has a “.grd” extension and is in XML format.

Notice that you cannot create a grid directly on a loaded image. You need before to load the image and after the grid above.

Aligning a grid on an image

Loading a grid

This is where all really begins. After having opened an image, you can load a grid on it.
To do this, you can use the “Grid>Load” menu or the following icon :

The selected grid will be loaded on the image, placed on the top left and the tab is divided into two parts, in order to add the table of spots characteristics.



	Name	X	Y	R	C	Block	Row	Column	Diameter	Computed Diameter
1	A01-A01	173.0	173.0	1	1	1	1	1	300.0	-1.0
2	A01-B01	519.0	173.0	1	2	1	1	2	300.0	-1.0
3	A01-C01	865.0	173.0	1	3	1	1	3	300.0	-1.0
4	A01-D01	1211.0	173.0	1	4	1	1	4	300.0	-1.0
5	A01-E01	1557.0	173.0	1	5	1	1	5	300.0	-1.0

The next step consists in correctly aligning the grid on the image.
You have several possibilities to do it. This step can be done manually or automatically by launching alignments algorithms.

All the alignment functionalities are available in the “Alignment” menu:



aligning manually a grid

How to manually place the grid?
You can either use the mouse and the “Move/Rotate/Resize” menu.
Let us present to you the “color code” of a grid: a loaded grid on an image appears in blue if it is not selected and orange if you select it.

To select in the grid, just click on it.
Note that you can easily only move a sub-grid by changing the selection mode:



These three icons of the toolbar allow to change the grid selection mode. By default, the first is enabled. It corresponds to the entire grid. If you select the second icon, you turn into the block mode that allows you to only select a block. The third icon corresponds to the spot mode that allows to only select one spot.

A selected item (spot, block or the grid) can be moved using the mouse. For this, move it by maintaining it selected (left mouse button down).
Notice that the table view corresponding selected spots lines are yellow.

Block selection mode	Spot selection mode
	

You can also deform the grid by placing your mouse at the corners and drag them.

A specific and useful tool allow to easily manually align a grid :the “Move/Rotate/Resize” menu.
Click on it: a window appears, offering you the possibility to rotate, move and resize the grid of given values:



Example: the grid has been moved and rotated.

You can choose the unit of your rotation (degrees, radian), the unit of your translation or resizing (pixels, µm or spots).

Thanks to this tool, you can manually correctly place the grid on the image. In order to verify the position of each spot, you can apply a “spot detection” (presented below).
Note that it is possible to perform an automatic local alignment on a manually aligned grid.

It is interesting to know how manually place a grid but in the most cases, you can perform automatic global and local alignments.
In the next pages we will see how to perform these automatic alignments.

Let us first introduce the notions of “global” and “local” alignments. The global alignment places the grid (as good as possible) on the entire image. The local alignment searches to correctly align each block separately.

These two algorithms have been initially developed for the BZScan software. So they have a lot of parameters that can be modified and memorized.

Global alignment algorithm



The “Global alignment” sub-menu contains two different algorithms, the “sniffer” and the “edges detection” global algorithms. The default algorithm is the “sniffer” one (in bold in the menu). You can also call it thanks to the following toolbar icon :

If you click on “Default algorithm”, it is launched without proposing you to change the parameters. To modify them, you need to choose the “Sniffer” menu. So the parameters windows appears:


Global alignment parameters
bloc alignment algorithm parameters
t : 0.1
c : 0.7
spot detection Algorithm : Detection by 4 profiles
Research area of the center (%) : 40
Computed area of the center (%) : 10
Quality threshold : 30
local alignment algorithm parameters
Bootstrap : sensitivity (%) : 20 Iterations number : 5
1st run : sensitivity (%) : 30 Iterations number : 50
2nd run : sensitivity (%) : 20 Iterations number : 10
3rd run : sensitivity (%) : 10 Iterations number : 10
Threshold of change of sensitivity : 1.0E-7
Vi¿½rifier la cohi¿½rence de la grille
10
Incrementation for the research of the angle (degrees) : 0,2
Contrast for the research of the angle (%) : 50
Size of the sniffer (spots) : 13
Apply
Close

Notice that all these parameters can be changed and saved. It is also always possible to restore the default parameters. So don't hesitate to change them. For more information about their meaning, please contact us.

"Sniffer" algorithm quick presentation:

At first, the angle of the image is calculated. Then (about 10% of the process), the algorithm try to parse all the image with a sniffer block to find all spots. To do this, it already searches to place the "sniffer block" (a defined block of spots) at 40% in width and in height of the image, the condition to place it is that the center spot must be a detected one. When the algorithm detects this spot, it considers this position as the first position of its route (pict1). The sniffer block moves after in all the direction of the image and flags every spot it finds. Each time it will find something considered a spot, it will put a little colored cross on its center (pict2). After having recovered the entire image, the algorithm computes how to place the grid in order to include the most of detected spots.
At the end of the process, you will have a yellow (selected) grid aligned on the image(pict3).

The Sniffer block	*Spots are found*	*Grid is placed*
		

Some visual steps of the sniffer global alignment.

Our grid is now globally aligned.
The next step of the process is the local alignment.

Local alignment algorithm

A local alignment is an alignment that you must launch on a "already aligned" grid. It allows to improve the alignment quality.
In the actual version, two different local alignment algorithms are available.



The "Local alignment" sub-menu contains two different algorithms, the "entire grid" and the "block by block" local alignment algorithms. The default algorithm is the "block by block" one (in bold in the menu). You can also call it thanks to the following toolbar icon :

If you click on “Default algorithm”, it is launched without proposing you to change the parameters. To modify them, you need to choose the “Alignment block by block” menu.

“Alignment block by block” algorithm quick presentation:
Each block is processed individually. The position of each spot is verified and adjusted. The block may be moved from the initial global alignment place.



Progression of the local algorithm

In this process, AGScan takes each block and tries to fit it as precisely as possible to the spots it finds underneath. Each block is processed separately and can therefore move from the previously calculated global position to a new one. It is quiet amazing to see how a block is progressing towards its end position. Once the block position is optimized, AGScan goes on with the next block.
The red circles indicate that the program identify a spot ; on the opposite, the green ones indicate that the spot is deduced due to the grid structure and the red spots locations.

Note that the coordinate values of the spots have changed during the local alignment process. You can see values in the alignment table.

The progress of the alignment is given by a progress bar.
At the end of the process your display windows will look like this :


AGScan - January 27, 2005 Version
File Edition Display Image Grid Alignment Quantification Batch Tools About
ALI_1139215929409.zaf

	Name	X	Y	R	C	Block	Row	Column	Diameter	Computed Diameter
1	A01-A01	3155.166	6108.49	1	1	1	1	1	300.0	-1.0
2	A01-B01	3498.975	6075.351	1	2	1	1	2	300.0	-1.0
3	A01-C01	3842.178	6037.527	1	3	1	1	3	300.0	-1.0

An aligned grid

Shortcut buttons

In the toolbar, you can see an icon like this one :

This icon permits to customize the two following icons :

Here is the selection window that opens when you click on it :



You can choose the default algorithm to use for global alignment and local alignement here.

As you can see on the previous picture, “Move it 2!” and “Sigenae Global Alignement” are plugin algorithms. In fact, if you own some global alignement plugins, there are dynamically add to the selection box.

Spot detection

The spot detection is the method used to define if a spot is found (red) or estimate (green). A spot is recognize as one if its form fit the model.
You can call it on a selected a grid. Indeed, a selected grid becomes orange, so you don't see the spot nature.



The “Spots detection” sub-menu contains two different algorithms, the “2 profiles” and the “4 profiles” algorithms. The default algorithm is the “4 profiles” one (in bold in the menu). You can also call it thanks to the toolbar icon :

If you click on “Default algorithm”, it is launch without propose you to change parameters. To modify them, you need to choose the “4 profiles” menu.

The “2 profiles” and the “4 profiles” spot detection algorithms are similar. The difference is that profiles of spots used to search the center of the spot since the center of the research zone are diagonal lines (for the “2 profiles” detection) and diagonals + vertical + horizontal lines (for the “4 profiles” detection).



2 profiles



4 profiles

These two methods progress rapidly and give you the percentage of detected spot in the status bar:



The table

When a grid is open, the main window is split into two parts, giving you access to a table view of the spot informations.
This table is synchronized with the alignment. So coordinates have been updated by the move of the grid. However, no new columns are added.



	Name	X	Y	R	C	Block	Row	Column	Diameter
86	A01-B08	3723.348	8476.989	8	2	1	8	2	300.0
87	A01-C08	4062.763	8455.912	8	3	1	8	3	300.0
88	A01-D08	4400.071	8391.421	8	4	1	8	4	300.0

A selected spot and its table description

Base columns are:
- the first column is the number of the spot, determined by the spotting plan.
- Name: ID of each spot defined by AGScan: the first part is the block ID, the second part is the spot ID. The letter corresponds to the line position (A,B.....) and the number is the column position (1,2,3,,,).
- X : X coordinate of the center of the spot in the image(in micrometer).
- Y : Y coordinate of the center of the spot in the image(in micrometer).
- R: row number in the entire grid.
- C: column number in the entire grid.
- Block: number of the current block.
- Row: row number in the current block.
- Column: column number in the current block.
- Diameter: constant diameter of the spot defined in the grid structure.

Note: the “Computed diameter” column is present but not used (values are “-1”) until the quantification is processed.

The table and the alignment are interactive. You can select a spot in the table and see its location at the same time on the alignment: the spot (or the set of spots) are highlighted into the alignment (see the figure above).

So it's also possible to sort columns values, copy it,color some values...



The columns options can be active by clicking on the right click of the mouse.
The interest of these options will be describe to you after the quantification part.

Quantifying an alignment

Now you have an aligned grid. So the next step is the quantification.

quantifications

Several computations are available. To launch a quantification, use the “Quantification>Compute” menu and select your action.
You can choose the type of quantification you want to call or select several of them with the “Selection” sub-menu or the following toolbar icon:



The selection menu opens the next window:
Here, you can choose the classic AGScan columns you want to process.
Alternatively, you can choose a quantification plugin in a list.



All installed plugins appears in the plugin list, and this list is dynamically generated (for example, if you install a new quantifiaction plugin, it will be added to the list).After selecting the actions you want to process, click on “OK”.
Each calculation is done one after the other. You can follow advance thanks to the progress bar.
Results are available into the table.

Computed Diameter	Qtf. Fit/Const.	Qtf. Fit/Calc.	Qtf. Image/Const.	Qtf. Image/Calc.	QM	Fit Correction	Overshining Correction
344.91243	18	22	33	42	0.6...	0.0	0.0
344.91243	21	27	32	46	0.6...	0.0	0.0

Example of columns added, results of quantifications

Note: the “Computed diameter” column is filled during quantifications that need this value.

By selecting the data column title, you can change its position in the table.

Available AGScan Quantifications:
Four quantification are available in AGScan:

- Image/Constant diameter Quantification: for each spot,the quantification value is computed thanks to the image pixels intensities and the constant diameter given by the grid structure.
- Image/Variable diameter Quantification: for each spot, the quantification value is computed thanks to the image pixels intensities and a variable computed diameter.
- Fit/Constant diameter Quantification:the quantification value is computed thanks to the estimated intensity of the spot (with a fit function) and the constant diameter given by the grid structure.
- Fit/Variable diameter Quantification: the quantification is computed thanks to the estimated intensity of the spot (with a fit function) and its variable computed diameter.

The QM value is an indication of quality of the spots. Each spot has a value of QM ranging between 0 and 1 (the closer the value is to 1, the more it is reliable).

The “fit correction” and the “overshining correction” are two corrections values that can be used with quantification. Be careful, to apply them, you need a specific formula.

analyze your results

Thanks to the table columns options, you can sort the result values,
Example of a sorted column: click right on the column header and choose “Sort> Descending Order”.

Qtf. Image/Co...
13759
12058
11290
10656
9888
9840
9275

An useful option is also the “color” tool. You can choose to give a color to some spots of the alignment in order to locate them.

Example: we want to color in orange spots that have an “image/constant” quantification value higher than 10000. To do that:

1/select the “Modify” menu of the “Qtf Image/Const” column.
2/Check the “superior” case, fill the value (10000) and choose a color(orange).



"Modify a column" window

3/Click on “Apply” and “Close”,
4/select the “Color spots” menu of the “Qtf Image/Const” column.
The text header of the column becomes red. Spots concerned by this condition will appear in orange on the aligned image.
In our example, only 4 spots are colored (as the sorted column shows us before).



Spot coloration example

You can also color spots between two values or lower than an other one.

Export results

You can save the experiment in every process step. An alignment and a quantification are considered as the same thing. In fact, there are two “aligned grid with a table”. Only tables columns differ. So use the “save” menu to save it. The extension of an experiment file is “.zaf”.

You can also export only the table values in order to use them into a spreadsheet.
To do that, select the menu:



"Quantification>Export>Text File" menu

The file saved content looks likes:

Block	Row	Column	Diameter	Computed Diameter	Qtf. Fit/Const.	Qtf. Fit/Calc.
1	1	1	300.0	344.91243	18	22
1	1	2	300.0	344.91243	21	27
1	1	3	300.0	344.91243	48	60
1	1	4	300.0	344.91243	11	14
1	1	5	300.0	344.91243	67	82
1	1	6	300.0	346.0	4475	5307
1	1	7	300.0	271.35695	4654	4397
1	1	8	300.0	344.91243	120	140
1	1	9	300.0	344.91243	46	58
1	1	10	300.0	346.0	3617	4098
1	1	11	300.0	344.91243	37	44
1	1	12	300.0	344.91243	27	32
1	2	1	300.0	344.91243	24	29
1	2	2	300.0	344.91243	11	14
1	2	3	300.0	286.43438	342	330
1	2	4	300.0	344.91243	176	212
1	2	5	300.0	121.14123	935	191
1	2	6	300.0	295.18784	1720	1720
1	2	7	300.0	344.91243	125	146
1	2	8	300.0	344.91243	18	23

Text file output example

Now, you have done a complete analyze of your image.
Do you know that this process can also be repeat automatically, using the batch mode?

Processing a batch

Batch tab

A batch allows to analyze automatically several experiments!

Important note: all these expermiments are analyzed with the same grid.

To create a batch, you can use the “File>Create>New Batch” menu or the “Batch>New Batch”.
The associated icon of the toolbar is:

The batch tab contains two parts:



"Batch" tab

The tab is split into two parts, the right part that displays experiments status and images open and the left part that contains the configuration of the batch.

Preparing the batch



Batch files configuration

In the top of the left part of the tab:
1/ Choose if the batch will work alignments or not (images).
1bis/ If you choose to process a batch working with images, select the number of channels for images.
2/ Click on the grid browse button and select the grid.
3/ Choose the output directory where results will be saved.
4/ Check or not the fact to save image into the archive created for each image. Notice that if the image isn't in the archive, you need to give its localization when you will open the experiment.

5/ Click on “Add Images” to select images.

Note: you can add images one by one or several in the same time in a multi-selection (only in “1 channel mode”).

After choosing several images: the right part is filled:

	Image 1	Image 2	Status
1	13309611z...	13309611z...	WAITING
2	13309611z...	13309611z...	WAITING

Batch experiment information

You can now choose all the actions you want to process for each image thanks to the job leftpart.



"Batch" parameters configuration

You just need to select the process you want in the two top lists and click on “Add” .

The added processes appear in the bottom list.
You must choose exactly one global alignement or/and one local alignment, and one quantification, else you won't be able to launch the batch.
Moreover, two options are available and could be added or not in any case :

- The snapshot mode : takes a photo of each alignment and save it in a jpeg file.
- The export results mode : save the quantification result in a text file.

If you mistape and add a process you do not want, you can select it and click on “Remove” to erase it from the bottom list.



To launch the batch, just click on “Launch”. **Following a "Batch" in progress**



When the batch starts, you can stretch the bar at top to follow the batch in progress.
The status of each image is updated.
In the statusbar of AGScan, the total percentage of the batch is given.

When the process is successfully finished, the image status is “DONE”.

	Image 1	Image 2	Status
1	13309611z...	13309611z...	DONE
2	13309611z...	13309611z...	DONE

Batch progress finished

When the batch is finished, you can see results in the output directory.

For each experiment, you will have:
– the archive .zaf file
– the snapshot .tif file (rapid snapshot of the alignment, optional)
– the export files (optional)

In our example, we have analyze two images and we asked for the text result file. So we have three files by image:

Elements of the output directory

Save/Open a batch

You can save a batch configuration in order to launch it several times or to re-open and modify it.
The extension of a batch file is a ".bzb". This file can only be used with AGScan. The format is kind of XML compliant.
Note:In the current version, it is not possible to record a batch in multichannel mode.

To open a batch, use the "File>Open>Batch" menu:



"File>Open>Batch" menu

Plugins

Presentation

One of the most interesting feature of AGScan is the plugins system.
It allows to easily add “functionalities” to AGScan.
For example, to add new file formats, alignment or quantification methods...
The only thing to do is to add plugins files in the agscan directory named “plugins”.

Some plugins are already available on the mulcyber following page:

Plugins

SPlotMatrixPlugin			**08/12/2005 14:28**	
SPlotMatrixPlugin.zip	18 KB	14 i386		.zip
SPlotPlugin			**08/12/2005 14:21**	
SPlotPlugin.zip	6 KB	12 i386		.zip
SAlignmentSnapshotPlugin			**06/12/2005 15:12**	
SAlignmentSnapshotPlugin.zip	3 KB	19 i386		.zip
SSurfacePlot_3DPlugin			**28/11/2005 16:04**	
SSurfacePlot_3DPlugin.zip	49 KB	17 i386		.zip
SSurfacePlot_3DPlugin_v2.zip	49 KB	0 i386		.zip
SQuantif1Plugin			**28/11/2005 15:13**	
SQuantif1Plugin.zip	27 KB	17 i386		.zip
SFilesMergePlugin			**24/11/2005 14:45**	
SFilesMergePlugin.zip	4 KB	27 i386		.zip
SMemoryPlugin			**24/11/2005 09:15**	
SMemoryPlugin.zip	6 KB	22 i386		.zip

Plugins download page

On the website, you can click on the name of the plugin to watch its presentation and on the .”zip” file to download it.

Example: the “Memory Plugin”

For example, we will present you how to download/install and run the SmemoryPlugin.
This plugin allows to add to AGScan a little window that give you the current memory consumption.

At first, click on the SMemoryPlugin.zip file to download it.
The .zip file contains sources, classes and compile notes (version of javac and AGScan used) of the Memory Controler plugin. Note that there are one source file SMemoryPlugin.java and 3 .class files (caused by embedded classes).
To use this plugin, just put .class files into the plugins directory of AGScan.
A "Memory Controler" submenu is added into the tool menu.



"Memory plugin" window

Notice that different categories of plugins exist. So, each plugin menu appears into its menu (alignment, tool, quantification...). There are also other plugins like “format plugins” that allow to read/save other images formats and that doesn't create menu into the application. You know that they are installed by showing the different type of files you can open. All these inforamtion are available int o the note provided with the plugin.

Frequently asked questions

(to be completed)

Index

Word Index

-Xmx 10
.bzb 7, 36
.grd 7, 18
.jar 10
.txt 7
.zaf 7, 31, 35
A
AGScan 1, 2, 4-13, 17, 24, 27, 29, 35-37
Alignment 4-7, 11, 15, 19, 21-24, 26, 27, 29, 31, 34, 35, 37, 38
B
Batch 4, 5, 7, 11, 31-36
Block 17, 19-24, 27
BZScan 4, 21, 37
C
ChangeLog.txt 10
D
Display window 11, 14
Download 4, 8, 9, 37
E
Export 4, 7, 31, 35
F
File formats 4, 7, 37
Fit correction 29
Fuji BAS5000 scanner 7
Full 9, 10, 45
G
Global alignment 4-6, 21-23
Grid 4, 6, 7, 11, 15-27, 29, 31, 33
Grid structure 4
I
Image 4, 6, 7, 11-16, 18, 19, 21, 22, 27, 29-31, 33, 35, 42
ImageJ 4, 10
INF/IMG 6
Intensity 5, 29
Interface 11, 45
ISAC 6, 7
J
Java Runtime Environment 9, 10
L
Languages 10, 12
Launcher configuration file 10
Level1 17
Level2 17
Light 9
Linux OS 10
Local alignment 4-6, 21, 23, 24
M
Menu bar 11
Mulcyber 4, 8, 37
O
Overshining correction 29
P
Packages contents 10
Plugin 4, 6, 37, 38
Plugins 4
Progress bar 11, 14, 24, 28
Properties 10, 12, 13, 15

Q
QM 29
Quantification 4-7, 11, 27-29, 31, 37, 38
S
Shortcuts 11, 12
SIGENAE 1, 4
Sniffer 21, 22
Spot 5, 6, 17, 20-24, 26, 27, 29, 30
Status bar 11, 15, 16, 26
Structure editor 16, 18
T
Tab 15, 16, 18, 32, 33, 35
Table 2, 7, 11, 16, 18, 20, 24, 26-29, 31
TIFF 6
Toolbar 11, 12, 19, 21, 23, 26, 28, 32
V
Versions 6, 9, 46
W
Windows OS 10
Z
Zoom 14-16

Illustration index

AGScan logo....1
Mulcyber AGScan page....8
Download AGScan....9
"Open" menu....12
"Open" shortcut....12
"Languages" window....12
"Open image" shortcut....12
"Open images" window....13
"image parameters" window....13
Radioactive experiment open....13
Cy3/Cy5 experiment open....14
"Image" menu....14
"Zoom" shortcut icon....14
A zoomed image....15
"Display" menu....15
"Windows" display mode & "Zoom window"....16
"Grid Structure Editor" window....17
Grid structures....18
"Load a grid" shortcut icon....18
"Alignment" menu....19
"Grid elements selection" shortcut icons....19
Sub-grid selection....20
"Move/Rotate/Resize" grid....20
"Global alignment" menu....21
"Global alignment" shortcut icon....21
"Global alignment parameters" window....22
"Sniffer" local alignment algorithm....22
"Local alignment" menu....23
"Lobal alignment" shortcut icon....23
Progression of the local algorithm....24
An aligned grid....25
"Spot detectiont" menu....26
"Spot detection" shortcut icon....26
Percentage of detected spots....26
A selected spot and its table description....27
Columns options....27
"Quantification>Compute>Selection" shortcut icon....28
"Quantification>Compute>Selection" menu....28
"Quantifications selection" window....28
Example of columns added, results of quantifications....29
A sorted column....29
"Modify a column" window....30
Spot coloration example....30
"Quantification>Export>Text File" menu....31
Example of output text file contents....31
"Batch" shortcut icon....32
"Batch" tab....32
"Batch" files configuration....33
Batch experiment information....33
"Batch" parameters configuration....34
Following a "Batch" in progress....35
Batch progress finished....35
Elements of the output directory....36
“File>Open>Batch” menu....36
Plugins download page....37
"Memory plugin" window....38

GNU GENERAL PUBLIC LICENSE

Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc.
51 Franklin St, Fifth Floor, Boston, MA 02110-1301, USA

Everyone is permitted to copy and distribute verbatim copies
of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Library General Public License instead.) You can apply it to your programs, too.
When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.
To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.
For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.
We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.
Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.
Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".
Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.
1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.
You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.
2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.

b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.

c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you

provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.
Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program. In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.
3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:

a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.
If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.
4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.
6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.
7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.
If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.
It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free

software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.
This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.
8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.
Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.
10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.
NO WARRANTY
11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.
12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.